# **ROI Polygon Editor (Tkinter GUI)**

#### **Features**

- Left-click to add points to a polygon
- Right-click to undo last point
- Double-click to complete the polygon and assign an ID
- Press 'C' to clear current polygon
- Press 'R' to reset all saved ROIs
- Press 'D' to delete a saved ROI by its ID
- Save all ROIs in structured JSON format

## Requirements

Install the required Python libraries (if not already installed):

pip install pillow

Tkinter is part of Python's standard library (no need to install separately in most cases).

### **How It Works**

- You load an image file via a file dialog.
- Start clicking on the image to mark ROI points.
- When a polygon is complete (min 3 points), double-click to finish and assign an ID.
- You can save all marked ROIs as a .json file.

#### How to Run

- 1. Save the script as roi\_editor.py
- 2. Open terminal or command prompt and run:

python roi\_editor.py

- 3. When prompted, select an image file (e.g., parking layout).
- 4. Use the mouse and keyboard shortcuts described below.

## **Controls & Shortcuts**

# **ROI Polygon Editor (Tkinter GUI)**

# **Sample Output (JSON Format)**

## **Output**

ROIs are saved as a list of objects:

Each with an "id" and a list of "coords" (x, y) representing the polygon.